

**Département
Architecture, Conception et Logiciels Embarqués**

**Exploration of Neural Networks & Benchmarking of
Computing Solutions with the N2D2 Platform**

Olivier Bichler, David Briand, Benjamin Bertelone

Wednesday 22nd February, 2017



Laboratoire d'Intégration des Systèmes et des Technologies

Commissariat à l'Energie Atomique et aux Energies Alternatives
Institut Carnot CEA LIST
Centre de Saclay | Nano-Innov Bât 862 | PC 172
91191 Gif sur Yvette Cedex
Tel. : +33 (0)1.69.08.49.67 | Fax : +33(0)1.69.08.83.95
thierry.collette@cea.fr

Établissement Public à caractère Industriel et Commercial RCS Paris B 775 685 019



Laboratoire d'Electronique et de Technologie de l'Information

Direction de la Recherche Technologique
Département Architecture Conception et Logiciels Embarqués



Contents

1	Presentation	5
1.1	Database handling	5
1.2	Data pre-processing	5
1.3	Deep network building	6
1.4	Performances evaluation	7
1.5	Hardware exports	7
1.6	Summary	9
2	Performing simulations	10
2.1	Obtaining the latest version of this manual	10
2.2	Obtaining N2D2	10
2.2.1	Prerequisites	10
2.2.2	Getting the sources	10
2.2.3	Compilation	10
2.3	Downloading training datasets	10
2.4	Run the learning	11
2.5	Test a learned network	11
2.5.1	Interpreting the results	11
	Recognition rate	11
	Confusion matrix	11
	Memory and computation requirements	12
	Kernels and weights distribution	12
	Output maps activity	12
2.6	Export a learned network	12
N2D2 IP only	2.6.1 C export	13
N2D2 IP only	2.6.2 CPP_OpenCL export	14
	2.6.3 CPP_cuDNN export	16
N2D2 IP only	2.6.4 C_HLS export	16
N2D2 IP only	2.6.5 PNeuro export	16
	INI configuration file	17
	Example	19
	Memory map	20
3	INI file interface	21
3.1	Global parameters	21
3.2	Databases	21
3.2.1	MNIST	21
3.2.2	GTSRB	21
3.2.3	Directory	22
3.2.4	Other built-in databases	23
	CIFAR10_Database	23
	CIFAR100_Database	23
	CKP_Database	23
	Caltech101_DIR_Database	24
	Caltech256_DIR_Database	24
	CaltechPedestrian_Database	24
	Daimler_Database	25
	FDDb_Database	25
	GTSDB_DIR_Database	25
	ILSVRC2012_Database	25

	KITTY_Database	25
	KITTY_Road_Database	25
	LITISRouen_Database	26
3.2.5	Dataset images slicing	26
3.3	Stimuli data analysis	26
3.3.1	Zero-mean and unity standard deviation normalization	26
3.3.2	Subtracting the mean image of the set	27
3.4	Environment	28
3.4.1	Built-in transformations	29
	AffineTransformation	30
	ApodizationTransformation	31
	ChannelExtractionTransformation	31
	ColorSpaceTransformation	32
	DFTTransformation	32
N2D2 IP only	DistortionTransformation	32
N2D2 IP only	EqualizeTransformation	32
N2D2 IP only	ExpandLabelTransformation	33
	FilterTransformation	33
	FlipTransformation	34
N2D2 IP only	GradientFilterTransformation	34
N2D2 IP only	LabelSliceExtractionTransformation	34
	MagnitudePhaseTransformation	34
N2D2 IP only	MorphologicalReconstructionTransformation	35
N2D2 IP only	MorphologyTransformation	35
	NormalizeTransformation	36
	PadCropTransformation	36
N2D2 IP only	RandomAffineTransformation	36
	RangeAffineTransformation	36
N2D2 IP only	RangeClippingTransformation	36
	RescaleTransformation	37
	ReshapeTransformation	37
N2D2 IP only	SliceExtractionTransformation	37
	ThresholdTransformation	37
	TrimTransformation	37
N2D2 IP only	WallisFilterTransformation	38
3.5	Network layers	38
3.5.1	Layer definition	38
3.5.2	Weight fillers	38
	ConstantFiller	38
	NormalFiller	38
	UniformFiller	39
	XavierFiller	39
3.5.3	Weight solvers	39
	SGDSolver_Frame	39
	SGDSolver_Frame_CUDA	40
3.5.4	Activation functions	41
	Logistic	41
	LogisticWithLoss	41
	Rectifier	41
	Saturation	41
	Softplus	41
	Tanh	41

	TanhLeCun	41
3.5.5	Conv	41
	Configuration parameters (<i>Frame</i> models)	42
	Configuration parameters (<i>Spike</i> models)	43
3.5.6	Deconv	44
	Configuration parameters (<i>Frame</i> models)	45
3.5.7	Pool	45
	Configuration parameters (<i>Spike</i> models)	46
3.5.8	FMP	46
	Configuration parameters (<i>Frame</i> models)	46
3.5.9	Fc	47
	Configuration parameters (<i>Frame</i> models)	47
	Configuration parameters (<i>Spike</i> models)	47
3.5.10	Rbf	48
	Configuration parameters (<i>Frame</i> models)	48
3.5.11	Softmax	49
3.5.12	LRN	49
	Configuration parameters (<i>Frame</i> models)	49
3.5.13	Dropout	50
	Configuration parameters (<i>Frame</i> models)	50
3.5.14	BatchNorm	50
	Configuration parameters (<i>Frame</i> models)	50
3.5.15	Transformation	51
4	Tutorials	52
4.1	Building a classifier neural network	52
4.2	Building a segmentation neural network	54
4.2.1	Faces detection	56
4.2.2	Gender recognition	57
4.2.3	ROIs extraction	57

1 Presentation

The N2D2 platform is a comprehensive solution for fast and accurate Deep Neural Network (DNN) simulation and full and automated DNN-based applications building. The platform integrates database construction, data pre-processing, network building, benchmarking and hardware export to various targets. It is particularly useful for DNN design and exploration, allowing simple and fast prototyping of DNN with different topologies. It is possible to define and learn multiple network topology variations and compare the performances (in terms of recognition rate and computational cost) automatically. Export targets include CPU, DSP and GPU with OpenMP, OpenCL, Cuda and CuDNN programming models as well as custom hardware IP code generation with High-Level Synthesis for FPGA and dedicated configurable DNN accelerator IP¹. The N2D2 platform also supports the PNeuro DNN programmable architecture².

In the following, the first section describes the database handling capabilities of the tool, which can automatically generate learning, validation and testing data sets from any hand made database (for example from simple files directories). The second section briefly describes the data pre-processing capabilities built-in the tool, which does not require any external pre-processing step and can handle many data transformation, normalization and augmentation (for example using elastic distortion to improve the learning). The third section show an example of DNN building using a simple INI text configuration file. The fourth section show some examples of metrics obtained after the learning and testing to evaluate the performances of the learned DNN. Next, the fifth section introduces the DNN hardware export capabilities of the toolflow, which can automatically generate ready to use code for various targets such as embedded GPUs or full custom dedicated FPGA IP. Finally, we conclude by summarising the main features of the tool.

1.1 Database handling

The tool integrates everything needed to handle custom or hand made databases:

- Genericity: load image and sound, 1D, 2D or 3D data;
- Associate a label for each data point (useful for scene labeling for example) or a single label to each data file (one object/class per image for example), 1D or 2D labels;
- Advanced Region of Interest (ROI) handling:
 - Support arbitrary ROI shapes (circular, rectangular, polygonal or pixelwise defined);
 - Convert ROIs to data point (pixelwise) labels;
 - Extract one or multiple ROIs from an initial dataset to create as many corresponding additional data to feed the DNN;
- Native support of file directory-based databases, where each sub-directory represents a different label. Most used image file formats are supported (JPEG, PNG, PGM...);
- Possibility to add custom datafile format in the tool without any change in the code base;
- Automatic random partitionning of the database into learning, validation and testing sets.

1.2 Data pre-processing

Data pre-processing, such as image rescaling, normalization, filtering... is directly integrated into the toolflow, with no need for external tool or pre-processing. Each pre-processing step is called a *transformation*.

The full sequence of transformations can be specified easily in a INI text configuration file. For example:

```
; First step: convert the image to grayscale
[env.Transformation-1]
Type=ChannelExtractionTransformation
```

¹Ongoing work

²Currently at the instruction set level

```

CSChannel=Gray

; Second step: rescale the image to a 29x29 size
[env.Transformation-2]
Type=RescaleTransformation
Width=29
Height=29

; Third step: apply histogram equalization to the image
[env.Transformation-3]
Type=EqualizeTransformation

; Fourth step (only during learning): apply random elastic distortions to the images to extent the
learning set
[env.OnTheFlyTransformation]
Type=DistortionTransformation
ApplyTo=LearnOnly
ElasticGaussianSize=21
ElasticSigma=6.0
ElasticScaling=20.0
Scaling=15.0
Rotation=15.0

```

Example of pre-processing transformations built-in in the tool are:

- Image color space change and color channel extraction;
- Elastic distortion;
- Histogram equalization (including CLAHE);
- Convolutional filtering of the image with custom or pre-defined kernels (Gaussian, Gabor...);
- (Random) image flipping;
- (Random) extraction of fixed-size slices in a given label (for multi-label images)
- Normalization;
- Rescaling, padding/cropping, trimming;
- Image data range clipping;
- (Random) extraction of fixed-size slices.

1.3 Deep network building

The building of a deep network is straightforward and can be done withing the same INI configuration file. Several layer types are available: convolutional, pooling, fully connected, Radial-basis function (RBF) and softmax. The tool is highly modular and new layer types can be added without any change in the code base. Parameters of each layer type are modifiable, for example for the convolutional layer, one can specify the size of the convolution kernels, the stride, the number of kernels per input map and the learning parameters (learning rate, initial weights value...). For the learning, the data dynamic can be chosen between 16 bits (with NVIDIA® CuDNN³), 32 bit and 64 bit floating point numbers.

The following example, which will serve as the use case for the rest of this presentation, shows how to build a DNN with 5 layers: one convolution layer, followed by one MAX pooling layer, followed by two fully connected layers and a softmax output layer.

```

; Specify the input data format
[env]
SizeX=24
SizeY=24
BatchSize=12

; First layer: convolutional with 3x3 kernels
[conv1]

```

³On future GPUs

```

Input=env
Type=Conv
KernelWidth=3
KernelHeight=3
NbChannels=32
Stride=1

; Second layer: MAX pooling with pooling area 2x2
[pool1]
Input=conv1
Type=Pool
Pooling=Max
PoolWidth=2
PoolHeight=2
NbChannels=32
Stride=2
Mapping.Size=1 ; one to one connection between convolution output maps and pooling input maps

; Third layer: fully connected layer with 60 neurons
[fc1]
Input=pool1
Type=Fc
NbOutputs=60

; Fourth layer: fully connected with 10 neurons
[fc2]
Input=fc1
Type=Fc
NbOutputs=10

; Final layer: softmax
[softmax]
Input=fc2
Type=Softmax
NbOutputs=10
WithLoss=1

[softmax.Target]
TargetValue=1.0
DefaultValue=0.0

```

The resulting DNN is shown in figure 1.

The learning is accelerated in GPU using the NVIDIA® CuDNN framework, integrated into the toolflow. Using GPU acceleration, learning times can be reduced typically by two orders of magnitude, enabling the learning of large databases within tens of minutes to a few hours instead of several days or weeks for non-GPU accelerated learning.

1.4 Performances evaluation

The software automatically outputs all the information needed for the network applicative performances analysis, such as the recognition rate and the validation score during the learning; the confusion matrix during learning, validation and test; the memory and computation requirements of the network; the output maps activity for each layer, and so on, as shown in figure 2.

1.5 Hardware exports

Once the learned DNN recognition rate performances are satisfying, an optimized version of the network can be automatically exported for various embedded targets. An automated network computation performances benchmarking can also be performed among different targets.

The following targets are currently supported by the toolflow:




Figure 1: Automatically generated and ready to learn DNN from the INI configuration file example.




Figure 2: Example of information automatically generated by the software during and after learning.

- Plain C code (no dynamic memory allocation, no floating point processing);
- C code accelerated with OpenMP;
- C code tailored for High-Level Synthesis (HLS) with Xilinx® Vivado® HLS;

Direct synthesis to FPGA, with timing and utilization after routing;

Possibility to constrain the maximum number of clock cycles desired to compute the whole network;

FPGA utilization vs number of clock cycle trade-off analysis;

- OpenCL code optimized for either CPU/DSP or GPU;
- Cuda kernels and CuDNN code optimized for NVIDIA® GPUs.

Different automated optimizations are embedded in the exports:

- DNN weights and signal data precision reduction (down to 8 bit integers or less for custom FPGA IPs);
- Non-linear network activation functions approximations;
- Different weights discretization methods.

The exports are generated automatically and come with a Makefile and a working testbench, including the pre-processed testing dataset. Once generated, the testbench is ready to be compiled and executed on the target platform. The applicative performance (recognition rate) as well as the computing time per input data can then be directly measured by the testbench.




Figure 3: Example of network benchmarking on different hardware targets.

The figure 3 shows an example of benchmarking results of the previous DNN on different targets (in log scale). Compared to desktop CPUs, the number of input image pixels processed per second is more than one order of magnitude higher with GPUs and at least two orders of magnitude better with synthesized DNN on FPGA.

1.6 Summary

The N2D2 platform is today a complete and production ready neural network building tool, which does not require advanced knowledges in deep learning to be used. It is tailored for fast neural network applications generation and porting with minimum overhead in terms of database creation and management, data pre-processing, networks configuration and optimized code generation, which can save months of manual porting and verification effort to a single automated step in the tool.

2 Performing simulations

2.1 Obtaining the latest version of this manual

Before going further, please make sure you are reading the latest version of this manual. It is located in the `manual` sub-directory. To compile the manual in PDF, just run the following command:

```
cd manual && make
```

2.2 Obtaining N2D2

2.2.1 Prerequisites

First, make sure you have the following packages installed:

- `gnuplot`
- `opencv`
- `opencv-devel` (on RHEL 6, requires `rhel-x86_64-workstation-optional-6` repository channel)

Plus, to be able to use GPU acceleration:

- `cuda`

To install `cuda`, add the `cuda` repository for RHEL 6:

```
rpm -Uvh http://developer.download.nvidia.com/compute/cuda/repos/rhel6/x86_64/cuda-repo-  
rhel6-7.5-18.x86_64.rpm  
yum clean expire-cache  
yum install cuda
```

Make sure the `cuda` library path (by default: `/usr/local/cuda/lib64`) is added to the `LD_LIBRARY_PATH` environment variable.

- `cudnn`

Manual installation required: register to [NVIDIA Developer](#) and download the latest version of CuDNN. Simply copy the header and library files from the CuDNN archive to the corresponding directories in the `cuda` installation path (by default: `/usr/local/cuda/include` and `/usr/local/cuda/lib64`, respectively).

2.2.2 Getting the sources

Use the following command:

```
git clone git@github.com:CEA-LIST/N2D2.git
```

2.2.3 Compilation

To compile the program:

```
mkdir build  
cd build  
cmake .. && make
```

2.3 Downloading training datasets

A python script located in the repository root directory allows you to automatically download some well-known datasets, like MNIST and GTSRB:

```
./tools/install_stimuli.py
```

By default, the datasets are downloaded in the path specified in the `N2D2_DATA` environment variable, which is the root path used by the N2D2 tool to locate the databases. If the `N2D2_DATA` variable is not set, the default value used is `/local/$USER/n2d2_data/` (or `/local/n2d2_data/` if the `USER` environment variable is not set) on Linux and `C:\n2d2_data\` on Windows.

2.4 Run the learning

The following command will run the learning for 600,000 image presentations/steps and log the performances of the network every 10,000 steps:

```
./n2d2 "mnist24_16c4s2_24c5s2_150_10.ini" -learn 600000 -log 10000
```

Note: you may want to check the gradient computation using the `-check` option. Note that it can be extremely long and can occasionally fail if the required precision is too high.

2.5 Test a learned network

After the learning is completed, this command evaluate the network performances on the test data set:

```
./n2d2 "mnist24_16c4s2_24c5s2_150_10.ini" -test
```

2.5.1 Interpreting the results

Recognition rate The recognition rate and the validation score are reported during the learning in the `TargetScore_*/Success_validation.png` file, as shown in figure 4.




Figure 4: Recognition rate and validation score during learning.

Confusion matrix The software automatically outputs the confusion matrix during learning, validation and test, with an example shown in figure 5. Each row of the matrix contains the number of occurrences estimated by the network for each label, for all the data corresponding to a single actual, target label. Or equivalently, each column of the matrix contains the number of actual, target label occurrences, corresponding to the same estimated label. Ideally, the matrix should be diagonal, with no occurrence of an estimated label for a different actual label (network mistake).

The confusion matrix reports can be found in the simulation directory:

- `TargetScore_*/ConfusionMatrix_learning.png`;




Figure 5: Example of confusion matrix obtained after the learning.

- *TargetScore_*/ConfusionMatrix_validation.png*;
- *TargetScore_*/ConfusionMatrix_test.png*.

Memory and computation requirements The software also report the memory and computation requirements of the network, as shown in figure 6. The corresponding report can be found in the *stats* sub-directory of the simulation.

Kernels and weights distribution The synaptic weights obtained during and after the learning can be analyzed, in terms of distribution (*weights* sub-directory of the simulation) or in terms of kernels (*kernels* sub-directory of the simulation), as shown in 7.

Output maps activity The initial output maps activity for each layer can be visualized in the *outputs_init* sub-directory of the simulation, as shown in figure 8.

2.6 Export a learned network

```
./n2d2 "mnist24_16c4s2_24c5s2_150_10.ini" -export CPP_OpenCL
```

Export types:

- *c* C export using OpenMP;
- *c_hls* C export tailored for HLS with Vivado HLS;
- *CPP_OpenCL* C++ export using OpenCL;
- *CPP_Cuda* C++ export using Cuda;
- *CPP_cuDNN* C++ export using CuDNN;
- *SC_Spike* SystemC spike export.

Other program options related to the exports:




Figure 6: Example of memory and computation requirements of the network.

Option [default value]	Description
-uenv	If present, treat the input stimuli data as unsigned
-nbbits [8]	
	Number of bits for the weights and signals. Must be 8, 16, 32 or 64 for integer export, or -32, -64 for floating point export. The number of bits can be arbitrary for the c_HLS export (for example, 6 bits)

2.6.1 C export

Test the exported network:

```
cd export_C_int8
make
./bin/n2d2_test
```

The result should look like:

```
...
1652.00/1762      (avg = 93.757094%)
1653.00/1763      (avg = 93.760635%)
1654.00/1764      (avg = 93.764172%)
Tested 1764 stimuli
Success rate = 93.764172%
Process time per stimulus = 187.548186 us (12 threads)
```

Confusion matrix:

/ T \ E /	0 /	1 /	2 /	3 /
/ 0 /	329 /	1 /	5 /	2 /
/ 1 /	97.63% /	0.30% /	1.48% /	0.59% /
/ 1 /	0 /	692 /	2 /	6 /
/ 2 /	0.00% /	98.86% /	0.29% /	0.86% /
/ 2 /	11 /	27 /	609 /	55 /




Figure 7: Example of kernels and weights distribution analysis for two convolutional layers.

/	/	1.57%	/	3.85%	/	86.75%	/	7.83%	/
/	3	/	0	/	0	/	1	/	24
/	/	0.00%	/	0.00%	/	4.00%	/	96.00%	/

T: Target E: Estimated

2.6.2 CPP_OpenCL export

The OpenCL export can run the generated program in GPU or CPU architectures. Compilation features:



Figure 8: Output maps activity example of the first convolutional layer of the network.

Preprocessor command [default value]	Description
PROFILING [0]	<p>Compile the binary with a synchronization between each layers and return the mean execution time of each layer. This preprocessor option can decrease performances.</p> <p>Generate the binary output of the OpenCL kernel .cl file use. The binary is store in the /bin folder. Indicate to the program to load an OpenCL kernel as a binary from the /bin folder instead of a .cl file.</p> <p>Use the CUDA OpenCL SDK locate at /usr/local/cuda</p> <p>Use the MALI OpenCL SDK locate at /usr/MaliOpenCLSDKvXXX</p> <p>Use the INTEL OpenCL SDK locate at /opt/intel/opencl</p> <p>Use the AMD OpenCL SDK locate at /opt/AMDAPPSDK - XXX</p>
GENERATE_KBIN [0]	
LOAD_KBIN [0]	
CUDA [0]	
MALI [0]	
INTEL [0]	
AMD [1]	

Program options related to the OpenCL export:

Option [default value]	Description
-cpu	<p>If present, force to use a CPU architecture to run the program</p> <p>If present, force to use a GPU architecture to run the program</p> <p>Size of the batch to use</p> <p>Path to a specific input stimulus to test. For example: -stimulus /stimulus/env0000.pgm command will test the file env0000.pgm of the stimulus folder.</p>
-gpu	
-batch [1]	
-stimulus [NULL]	

Test the exported network:

```
cd export_CPP_OpenCL_float32
make
./bin/n2d2_openc1_test -gpu
```

2.6.3 CPP_cuDNN export

The cuDNN export can run the generated program in NVIDIA GPU architecture. It use CUDA and cuDNN library. Compilation features:

Preprocessor command [default value]	Description
PROFILING [0]	Compile the binary with a synchronization between each layers and return the mean execution time of each layer. This preprocessor option can decrease performances.
ARCH32 [0]	Compile the binary with the 32-bits architecture compatibility.

Program options related to the cuDNN export:

Option [default value]	Description
-batch [1]	Size of the batch to use
-dev [0]	CUDA Device ID selection
-stimulus [NULL]	Path to a specific input stimulus to test. For example: -stimulus /stimulus/env0000.pgm command will test the file env0000.pgm of the stimulus folder.

Test the exported network:

```
cd export_CPP_cuDNN_float32
make
./bin/n2d2_cudnn_test
```

2.6.4 C_HLS export

Test the exported network:

```
cd export_C_HLS_int8
make
./bin/n2d2_test
```

Run the High-Level Synthesis (HLS) with Xilinx® Vivado® HLS:

```
vivado_hls -f run_hls.tcl
```

2.6.5 PNeuro export

Exports allow generating standalone systems from calibrated neural network.

Can be used from the neural network directory using :

```
./test.sh -export <export_target> [-no-db-export] [-export-parameters <export_paramaters|">"] [-nbbits <number_of_bits|8>]
```

Where <export_target> is the target system, can be C, C++, PNeuro... (see below for a more detailed list), -no-db-export to disable the database export, <export_paramaters> are specific parameters for each export, default empty, and <number_of_bits> is the number of bits to use during export, positive for integer, negative for float, default 8.

PNeuro export generates code for PNeuro and memory blocks.

The <export_paramaters> need to be the path to an INI configuration file which describe the global behaviour and memory accesses. This export can only be done in 8 bits.

INI configuration file Each sections of the INI file refers to neural network layer by its name. Only Conv, Pool and Fc layers are supported. The order of sections determines the order of execution on the PNeuro.

The global parameters :

Option [default value]	Description
outputFile [pneuro.pas]	Output filename
weightsDir [weights]	Directory to place weights
kernelsDir [kernels]	Directory to place kernels
neuroBlock [1]	Number of NeuroBlock to use (1/2/4)

Each layers All layers have those parameters :

Option [default value]	Description
in [0m(0)]	Base address for input data
inFmGap [0]	Gap, in word, they have between each input feature map
out [0m(0)]	Base address for output data
outFmGap [0]	Gap, in word, to leave between each output feature map

Convolutional layers

Option [default value]	Description
weightsIn [0m(0)]	Base address for weights
weightsInOffset [0]	<i>Horizontal</i> offset for weights (0 = full left)
loadWeights [onInit]	Time to load weights in memory (onInit/onStart/onTheFly)
sign [us]	Signs of operation, first letter for inputs, second weights

Parameters available after processing for further usage :

Parameter	Description
_in_after	Address just after the last input
_out_after	Address just after the last output
_weights_after	Address just after the last weight

Limitations

Kernel

Width of the kernel is limited by :

$$1 \leq Kernel_{width} \leq 2 * M + 1$$

Where M is the interleaving, defined by :

$$M = ceil \left(\frac{Input_{width}}{8 * Nb_{NeuroBlock}} \right)$$

Height of the kernel is limited by :

$$1 \leq Kernel_{height} \leq 8 - WeightsOffset_x$$

Padding

X padding is limited by :

$$Kernel_{width} - M - 1 \leq Padding_x \leq M$$

Y padding isn't limited.

Stride

X stride is limited by :

$$\begin{cases} 1 \leq Stride_x \leq M \\ M \equiv 0 \pmod{Stride_x} \end{cases}$$

Y stride is limited by :

$$1 \leq Stride_y$$

Activation Function

Only TanH and Rectifier are currently supported.

Pooling layers

Option [default value]	Description
sign [s]	Sign of operation
fullSize [0]	Force to compute missing pixels (do not use)

Parameters available after processing for further usage :

Parameter	Description
_in_after	Address just after the last input
_out_after	Address just after the last output

Limitations

Kernel & Stride

Width of the kernel and X stride are limited by :

$$\begin{cases} 1 \leq Kernel_{width} \leq M \\ M \equiv 0 \pmod{Kernel_{width}} \\ Stride_x = Kernel_{width} \end{cases}$$

Where M is the interleaving, defined by :

$$M = \text{ceil} \left(\frac{Input_{width}}{8 * Nb_{NeuroBlock}} \right)$$

Height of the kernel and Y stride are limited by :

$$\begin{cases} 1 \leq Kernel_{height} \\ Stride_y = Kernel_{width} \end{cases}$$

Padding

X padding is limited by :

$$Kernel_{width} - M - 1 \leq Padding_x \leq M$$

Y padding isn't limited.

Fully Connected layers

Option [default value]	Description
weightMemA [0m(0)]	Base address for weights in first memory
weightMemB [0m(0)]	Base address for weights in second memory
loadWeights [onTheFly]	Time to load weights in memory (onInit/onStart/onTheFly)
sign [ss]	Signs of operation, first letter for inputs, second weights
inputType [auto]	Set the type of the previous layer (auto/2d/fc)

Parameters available after processing for further usage :

Parameter	Description
_in_after	Address just after the last input
_out_after	Address just after the last output
_temp_after	Address just after the last temporary value
_weightsMemA_after	Address just after the last weight of first memory
_weightsMemB_after	Address just after the last weight of second memory

Limitations

Activation Function

Only TanH and Rectifier are currently supported.




Figure 9: Example of Neural Network for PNeuro export

Example Associated INI configuration file :

```
neuroBlock=1

[conv1_3x3]
in=3m(512)
inFmGap=6
out=2m(0)
weightsIn=1m(0)
weightsInOffset=0
loadWeights=onInit
sign=us

[pool1_3x3]
in=[conv1_3x3]out
out=3m(0)
sign=s

[conv1_5x5]
```

```

in=3m(512)
inFmGap=6
out=2m(0)
weightsIn=1m(0)
weightsInOffset=3
loadWeights=onInit
sign=ss

[pool1_5x5]
in=[conv1_5x5]out
out=[pool1_3x3]_out_after
sign=s

[fc1]
in=[pool1_3x3]out
out=2m(0)
weightMemA=1m(26)
weightMemB=0m(0)
loadWeights=onTheFly
sign=ss

[fc2]
in=[fc1]out
out=3m(0)
weightMemA=[conv1_5x5]_weights_after
weightMemB=0m(0)
loadWeights=onInit
sign=ss

```

Memory map Memory map is generating during the export.

The file memories.data describes the memory map.

Each lines are a new subpart. They start with the neuroblock, then the first address and then the size of the subpart.

The files <loadWeights>-<subpart>-<neuroblock>.data are the content of memories. 4 LSB first then 4 MSB.

3 INI file interface

3.1 Global parameters

Option [default value]	Description
DefaultModel [Transcode]	Default layers model. Can be Frame, Frame_CUDA, Transcode or Spike
SignalsDiscretization [0]	Number of levels for signal discretization
FreeParametersDiscretization [0]	Number of levels for weights discretization

3.2 Databases

The tool integrates pre-defined modules for several well-known database used in the deep learning community, such as MNIST, GTSRB, CIFAR10 and so on. That way, no extra step is necessary to be able to directly build a network and learn it on these database.

3.2.1 MNIST

MNIST ([LeCun et al., 1998](#)) is already fractionned into a learning set and a testing set, with:

- 60,000 digits in the learning set;
- 10,000 digits in the testing set.

Example:

```
[database]
Type=MNIST_IDX_Database
Validation=0.2 ; Fraction of learning stimuli used for the validation [default: 0.0]
```

Option [default value]	Description
Validation [0.0]	Fraction of the learning set used for validation
DataPath [\$N2D2_DATA/mnist]	Path to the database

3.2.2 GTSRB

GTSRB ([Stallkamp et al., 2012](#)) is already fractionned into a learning set and a testing set, with:

- 39,209 digits in the learning set;
- 12,630 digits in the testing set.

Example:

```
[database]
Type=GTSRB_DIR_Database
Validation=0.2 ; Fraction of learning stimuli used for the validation [default: 0.0]
```

Option [default value]	Description
Validation [0.0]	Fraction of the learning set used for validation
DataPath [\$N2D2_DATA/GTSRB]	Path to the database

3.2.3 Directory

Hand made database stored in files directories are directly supported with the `DIR_Database` module. For example, suppose your database is organized as following (in the path specified in the `N2D2_DATA` environment variable):

- GST/airplanes: 800 images
- GST/car_side: 123 images
- GST/Faces: 435 images
- GST/Motorbikes: 798 images

You can then instantiate this database as input of your neural network using the following parameters:

```
[database]
Type=DIR_Database
DataPath=${N2D2_DATA}/GST
Learn=0.4 ; 40% of images of the smallest category = 49 (0.4x123) images for each category will be
            used for learning
Validation=0.2 ; 20% of images of the smallest category = 25 (0.2x123) images for each category
                will be used for validation
; the remaining images will be used for testing
```

Each subdirectory will be treated as a different label, so there will be 4 different labels, named after the directory name.

The stimuli are equi-partitioned for the learning set and the validation set, meaning that the same number of stimuli for each category is used. If the learn fraction is 0.4 and the validation fraction is 0.2, as in the example above, the partitioning will be the following:

Label ID	Label name	Learn set	Validation set	Test set
0	airplanes	49	25	726
1	car_side	49	25	49
2	Faces	49	25	361
3	Motorbikes	49	25	724
Total:		196	100	1860

 *Mandatory option*

Option [default value]	Description
DataPath Learn	Path to the root stimuli directory If <code>PerLabelPartitioning</code> is true, fraction of images used for the learning; else, number of images used for the learning, regardless of their labels
LoadInMemory [0] Depth [1]	Load the whole database into memory Number of sub-directory levels to include. Examples: <code>Depth = 0</code> : load stimuli only from the current directory (<code>DataPath</code>) <code>Depth = 1</code> : load stimuli from <code>DataPath</code> and stimuli contained in the sub-directories of <code>DataPath</code> <code>Depth < 0</code> : load stimuli recursively from <code>DataPath</code> and all its sub-directories
LabelName [] LabelDepth [1]	Base stimuli label name Number of sub-directory name levels used to form the stimuli labels. Examples: <code>LabelDepth = -1</code> : no label for all stimuli (label ID = -1)

PerLabelPartitioning [1] Validation [0.0] Test [1.0-Learn-Validation]	LabelDepth = 0: uses LabelName for all stimuli LabelDepth = 1: uses LabelName for stimuli in the current directory (DataPath) and LabelName/sub-directory name for stimuli in the sub-directories If true, the stimuli are equi-partitioned for the learn/validation/test sets, meaning that the same number of stimuli for each label is used If PerLabelPartitioning is true, fraction of images used for the validation; else, number of images used for the validation, regardless of their labels If PerLabelPartitioning is true, fraction of images used for the test; else, number of images used for the test, regardless of their labels
ROIFile [] DefaultLabel [] ROIsMargin [0]	File containing the stimuli ROIs. If a ROI file is specified, LabelDepth should be set to -1 Label name for pixels outside any ROI (default is no label, pixels are ignored) Number of pixels around ROIs that are ignored (and not considered as DefaultLabel pixels)

3.2.4 Other built-in databases

CIFAR10_Database CIFAR10 database ([Krizhevsky, 2009](#)).

Option [default value]	Description
Validation [0.0] DataPath [\$N2D2_DATA/cifar-10-batches-bin]	Fraction of the learning set used for validation Path to the database

CIFAR100_Database CIFAR100 database ([Krizhevsky, 2009](#)).

Option [default value]	Description
Validation [0.0] UseCoarse [0] DataPath [\$N2D2_DATA/cifar-100-binary]	Fraction of the learning set used for validation If true, use the coarse labeling (10 labels instead of 100) Path to the database

CKP_Database The Extended Cohn-Kanade (CK+) database for expression recognition ([Lucey et al., 2010](#)).

Option [default value]	Description
Learn Validation [0.0] DataPath [\$N2D2_DATA/cohn-kanade-images]	Fraction of images used for the learning Fraction of images used for the validation Path to the database

Caltech101_DIR_Database Caltech 101 database (Fei-Fei et al., 2004).

Option [default value]	Description
Learn	Fraction of images used for the learning
Validation [0.0]	Fraction of images used for the validation
IncClutter [0]	If true, includes the BACKGROUND_Google directory of the database
DataPath [\$N2D2_DATA/ 101_ObjectCategories]	Path to the database

Caltech256_DIR_Database Caltech 256 database (Griffin et al., 2007).

Option [default value]	Description
Learn	Fraction of images used for the learning
Validation [0.0]	Fraction of images used for the validation
IncClutter [0]	If true, includes the BACKGROUND_Google directory of the database
DataPath [\$N2D2_DATA/ 256_ObjectCategories]	Path to the database

CaltechPedestrian_Database Caltech Pedestrian database (Dollár et al., 2009).

Note that the images and annotations must first be extracted from the seq video data located in the *videos* directory using the `dbExtract.m` Matlab tool provided in the "Matlab evaluation/labeling code" downloadable on the dataset website.

Assuming the following directory structure (in the path specified in the `N2D2_DATA` environment variable):

- CaltechPedestrians/data-USA/videos/... (from the *setxx.tar* files)
- CaltechPedestrians/data-USA/annotations/... (from the *setxx.tar* files)
- CaltechPedestrians/tools/piotr_toolbox/toolbox (from the Piotr's Matlab Toolbox archive)
- CaltechPedestrians/*.m including `dbExtract.m` (from the Matlab evaluation/labeling code)

Use the following command in Matlab to generate the images and annotations:

```
cd([getenv('N2D2_DATA') '/CaltechPedestrians'])
addpath(genpath('tools/piotr_toolbox/toolbox')) % add the Piotr's Matlab Toolbox in the Matlab
path
dbInfo('USA')
dbExtract()
```

Option [default value]	Description
Validation [0.0]	Fraction of the learning set used for validation
SingleLabel [1]	Use the same label for "person" and "people" bounding box
IncAmbiguous [0]	Include ambiguous bounding box labeled "person?" using the same label as "person"
DataPath [\$N2D2_DATA/ CaltechPedestrians/data- USA/images]	Path to the database images
LabelPath [\$N2D2_DATA/ CaltechPedestrians/data- USA/annotations]	Path to the database annotations

Daimler_Database Daimler Monocular Pedestrian Detection Benchmark (Daimler Pedestrian).

Option [default value]	Description
Learn [1.0]	Fraction of images used for the learning
Validation [0.0]	Fraction of images used for the validation
Test [0.0]	Fraction of images used for the test
Fully [0]	When activate it use the test dataset to learn. Use only on fully-cnn mode

FDDB_Database Face Detection Data Set and Benchmark (FDDB) ([Jain and Learned-Miller, 2010](#)).

Option [default value]	Description
Learn	Fraction of images used for the learning
Validation [0.0]	Fraction of images used for the validation
DataPath [\$N2D2_DATA/FDDB]	Path to the images (decompressed originalPics.tar.gz)
LabelPath [\$N2D2_DATA/FDDB]	Path to the annotations (decompressed FDDB-folds.tgz)

GTSDb_DIR_Database GTSDb database ([Houben et al., 2013](#)).

Option [default value]	Description
Learn	Fraction of images used for the learning
Validation [0.0]	Fraction of images used for the validation
DataPath [\$N2D2_DATA/FullIJCNN2013]	Path to the database

ILSVRC2012_Database ILSVRC2012 database ([Russakovsky et al., 2015](#)).

Option [default value]	Description
Learn	Fraction of images used for the learning
DataPath [\$N2D2_DATA/ILSVRC2012]	Path to the database
LabelPath [\$N2D2_DATA /ILSVRC2012/synsets.txt]	Path to the database labels list file

KITTY_Database KITTY Database.

Option [default value]	Description
Learn [0.8]	Fraction of images used for the learning
Validation [0.2]	Fraction of images used for the validation

KITTY_Road_Database KITTY Road Database. The KITTY Road Database provide ROI which can be used to road segmentation.

Option [default value]	Description
Learn [0.8]	Fraction of images used for the learning
Validation [0.2]	Fraction of images used for the validation

LITISRouen_Database LITIS Rouen audio scene dataset ([Rakotomamonjy and Gasso, 2014](#)).

Option [default value]	Description
Learn [0.4]	Fraction of images used for the learning
Validation [0.4]	Fraction of images used for the validation
DataPath	Path to the database
[\$N2D2_DATA/data_rouen]	

3.2.5 Dataset images slicing

It is possible to automatically slice images from a dataset, with a given slice size and stride, using the `.slicing` attribute. This effectively increases the number of stimuli in the set.

```
[database.slicing]
```

```
ApplyTo=NoLearn
Width=2048
Height=1024
StrideX=2048
StrideY=1024
```

3.3 Stimuli data analysis

You can enable stimuli data reporting with the following section (the name of the section must start with `env.StimuliData`):

```
[env.StimuliData-raw]
```

```
ApplyTo=LearnOnly
LogSizeRange=1
LogValueRange=1
```

The stimuli data reported for the full MNIST learning set will look like:

```
env.StimuliData-raw data:
Number of stimuli: 60000
Data width range: [28, 28]
Data height range: [28, 28]
Data channels range: [1, 1]
Value range: [0, 255]
Value mean: 33.3184
Value std. dev.: 78.5675
```

3.3.1 Zero-mean and unity standard deviation normalization

It is possible to normalize the whole database to have zero mean and unity standard deviation on the learning set using a `RangeAffineTransformation` transformation:

```
; Stimuli normalization based on learning set global mean and std.dev.
```

```
[env.Transformation-normalize]
```

```
Type=RangeAffineTransformation
FirstOperator=Minus
FirstValue=[env.StimuliData-raw]_GlobalValue.mean
SecondOperator=Divides
SecondValue=[env.StimuliData-raw]_GlobalValue.stdDev
```

The variables `_GlobalValue.mean` and `_GlobalValue.stdDev` are automatically generated in the `[env.StimuliData-raw]` block. Thanks to this facility, unknown and arbitrary database can be analysed and normalized in one single step without requiring any external data manipulation.

After normalization, the stimuli data reported is:

```

env.StimuliData-normalized data:
Number of stimuli: 60000
Data width range: [28, 28]
Data height range: [28, 28]
Data channels range: [1, 1]
Value range: [-0.424074, 2.82154]
Value mean: 2.64796e-07
Value std. dev.: 1

```

Where we can check that the global mean is close to 0 and the standard deviation is 1 on the whole dataset. The result of the transformation on the first images of the set can be checked in the generated *frames* folder, as shown in figure 10.




Figure 10: Image of the set after normalization.

3.3.2 Subtracting the mean image of the set

Using the *StimuliData* object followed with an *AffineTransformation*, it is also possible to use the mean image of the dataset to normalize the data:

```

[env.StimuliData-meanData]
ApplyTo=LearnOnly
MeanData=1 ; Provides the _MeanData parameter used in the transformation

[env.Transformation]
Type=AffineTransformation
FirstOperator=Minus
FirstValue=[env.StimuliData-meanData]_MeanData

```

The resulting global mean image can be visualized in *env.StimuliData-meanData/meanData.bin.png* and is shown in figure 11.

After this transformation, the reported stimuli data becomes:

```

env.StimuliData-processed data:
Number of stimuli: 60000
Data width range: [28, 28]

```




Figure 11: Global mean image generated by `StimuliData` with the `MeanData` parameter enabled.

Data height range: [28, 28]
Data channels range: [1, 1]
Value range: [-139.554, 254.979]
Value mean: -3.45583e-08
Value std. dev.: 66.1288

The result of the transformation on the first images of the set can be checked in the generated `frames` folder, as shown in figure 12.

3.4 Environment

The environment simply specify the input data format of the network (width, height and batch size). Example:

```
[env]
SizeX=24
SizeY=24
BatchSize=12 ; [default: 1]
```

Option [default value]	Description
SizeX	Environment width
SizeY	Environment height
NbChannels [1]	Number of channels (applicable only if there is no <code>env. ChannelTransformation[...]</code>)
BatchSize [1]	Batch size
CompositeStimuli [0]	If true, use pixel-wise stimuli labels
CachePath []	Stimuli cache path (no cache if left empty)
StimulusType [SingleBurst]	Method for converting stimuli into spike trains. Can be any of <code>SingleBurst</code> , <code>Periodic</code> , <code>JitteredPeriodic</code> OR <code>Poissonian</code>

DiscardedLateStimuli [1.0]	The pixels in the pre-processed stimuli with a value above this limit never generate spiking events
PeriodMeanMin [50 TimeMs]	Mean minimum period $\overline{T_{min}}$, used for periodic temporal codings, corresponding to pixels in the pre-processed stimuli with a value of 0 (which are supposed to be the most significant pixels)
PeriodMeanMax [12 TimeS]	Mean maximum period $\overline{T_{max}}$, used for periodic temporal codings, corresponding to pixels in the pre-processed stimuli with a value of 1 (which are supposed to be the least significant pixels). This maximum period may be never reached if DiscardedLateStimuli is lower than 1.0
PeriodRelStdDev [0.1]	Relative standard deviation, used for periodic temporal codings, applied to the spiking period of a pixel
PeriodMin [11 TimeMs]	Absolute minimum period, or spiking interval, used for periodic temporal codings, for any pixel

3.4.1 Built-in transformations

There are 6 possible categories of transformations:

- `env.Transformation[...]` Transformations applied to the input images before channels creation;
- `env.OnTheFlyTransformation[...]` On-the-fly transformations applied to the input images before channels creation;
- `env.ChannelTransformation[...]` Create or add transformation for a specific channel;
- `env.ChannelOnTheFlyTransformation[...]` Create or add on-the-fly transformation for a specific channel;
- `env.ChannelsTransformation[...]` Transformations applied to all the channels of the input images;
- `env.ChannelsOnTheFlyTransformation[...]` On-the-fly transformations applied to all the channels of the input images.

Example:

```
[env.Transformation]
Type=PadCropTransformation
Width=24
Height=24
```

Several transformations can be applied successively. In this case, to be able to apply multiple transformations of the same category, a different suffix ([...]) must be added to each transformation.

The transformations will be processed in the order of appearance in the INI file regardless of their suffix.

Common set of parameters for any kind of transformation:

Option [default value]	Description
ApplyTo [All]	Apply the transformation only to the specified stimuli sets. Can be: LearnOnly: learning set only ValidationOnly: validation set only TestOnly: testing set only NoLearn: validation and testing sets only NoValidation: learning and testing sets only NoTest: learning and validation sets only All: all sets (default)




Figure 12: Image of the set after the **AffineTransformation** subtracting the global mean image (keep in mind that the original image value range is $[0, 255]$).

Example:

```
[env.Transformation-1]
Type=ChannelExtractionTransformation
CSChannel=Gray

[env.Transformation-2]
Type=RescaleTransformation
Width=29
Height=29

[env.Transformation-3]
Type=EqualizeTransformation

[env.OnTheFlyTransformation]
Type=DistortionTransformation
ApplyTo=LearnOnly ; Apply this transformation for the Learning set only
ElasticGaussianSize=21
ElasticSigma=6.0
ElasticScaling=20.0
Scaling=15.0
Rotation=15.0
```

List of available transformations:

AffineTransformation Apply an element-wise affine transformation to the image with matrixes of the same size.

Option [default value]	Description
FirstOperator	First element-wise operator, can be Plus, Minus, Multiplies, Divides First matrix file name Second element-wise operator, can be Plus, Minus, Multiplies, Divides Second matrix file name
FirstValue	
SecondOperator [Plus]	
SecondValue []	

The final operation is the following, with A the image matrix, B_{1st} , B_{2nd} the matrixes to add/subtract/multiply/divide and \odot the element-wise operator :

$$f(A) = (A \odot_{op_{1st}} B_{1st}) \odot_{op_{2nd}} B_{2nd}$$

ApodizationTransformation Apply an apodization window to each data row.

Option [default value]	Description
Size	Window total size (must match the number of data columns) Window name. Possible values are: Rectangular: Rectangular Hann: Hann Hamming: Hamming Cosine: Cosine Gaussian: Gaussian Blackman: Blackman Kaiser: Kaiser
WindowName [Rectangular]	

Gaussian window Gaussian window.

Option [default value]	Description
<i>WindowName.Sigma</i> [0.4]	Sigma

Blackman window Blackman window.

Option [default value]	Description
<i>WindowName.Alpha</i> [0.16]	Alpha

Kaiser window Kaiser window.

Option [default value]	Description
<i>WindowName.Beta</i> [5.0]	Beta

ChannelExtractionTransformation Extract an image channel.

Option	Description
CSChannel	Blue: blue channel in the BGR colorspace, or first channel of any colorspace Green: green channel in the BGR colorspace, or second channel of any colorspace Red: red channel in the BGR colorspace, or third channel of any colorspace Hue: hue channel in the HSV colorspace Saturation: saturation channel in the HSV colorspace Value: value channel in the HSV colorspace Gray: gray conversion Y: Y channel in the YCbCr colorspace Cb: Cb channel in the YCbCr colorspace Cr: Cr channel in the YCbCr colorspace

ColorSpaceTransformation Change the current image colorspace.

Option	Description
ColorSpace	BGR: if the image is in grayscale, convert it in BGR HSV HLS YCrCb CIELab CIEluv

DFTTransformation Apply a DFT to the data. The input data must be single channel, the resulting data is two channels, the first for the real part and the second for the imaginary part.

Option [default value]	Description
TwoDimensional [1]	If true, compute a 2D image DFT. Otherwise, compute the 1D DFT of each data row

Note that this transformation can add zero-padding if required by the underlying FFT implementation.

N2D2 IP only **DistortionTransformation** Apply elastic distortion to the image. This transformation is generally used on-the-fly (so that a different distortion is performed for each image), and for the learning only.

Option [default value]	Description
ElasticGaussianSize [15]	Size of the gaussian for elastic distortion (in pixels)
ElasticSigma [6.0]	Sigma of the gaussian for elastic distortion
ElasticScaling [0.0]	Scaling of the gaussian for elastic distortion
Scaling [0.0]	Maximum random scaling amplitude (+/-, in percentage)
Rotation [0.0]	Maximum random rotation amplitude (+/-, in °)

N2D2 IP only **EqualizeTransformation** Image histogram equalization.

Option [default value]	Description
Method [Standard]	Standard: standard histogram equalization
CLAHE_ClipLimit [40.0]	CLAHE: contrast limited adaptive histogram equalization
CLAHE_GridSize [8]	Threshold for contrast limiting (for CLAHE only) Size of grid for histogram equalization (for CLAHE only). Input image will be divided into equally sized rectangular tiles. This parameter defines the number of tiles in row and column.

ExpandLabelTransformation Expand single image label (1x1 pixel) to full frame label.

FilterTransformation Apply a convolution filter to the image.

Option [default value]	Description
Kernel	Convolution kernel. Possible values are: *: custom kernel Gaussian: Gaussian kernel LoG: Laplacian Of Gaussian kernel DoG: Difference Of Gaussian kernel Gabor: Gabor kernel

* **kernel** Custom kernel.

Option	Description
Kernel.SizeX [0]	Width of the kernel (number of columns)
Kernel.SizeY [0]	Height of the kernel (number of rows)
Kernel.Mat	List of row-major ordered coefficients of the kernel

If both `Kernel.SizeX` and `Kernel.SizeY` are 0, the kernel is assumed to be square.

Gaussian kernel Gaussian kernel.

Option [default value]	Description
Kernel.SizeX	Width of the kernel (number of columns)
Kernel.SizeY	Height of the kernel (number of rows)
Kernel.Positive [1]	If true, the center of the kernel is positive
Kernel.Sigma [$\sqrt{2.0}$]	Sigma of the kernel

LoG kernel Laplacian Of Gaussian kernel.

Option [default value]	Description
Kernel.SizeX	Width of the kernel (number of columns)
Kernel.SizeY	Height of the kernel (number of rows)
Kernel.Positive [1]	If true, the center of the kernel is positive
Kernel.Sigma [$\sqrt{2.0}$]	Sigma of the kernel

DoG kernel Difference Of Gaussian kernel kernel.

Option [default value]	Description
Kernel.SizeX	Width of the kernel (number of columns)
Kernel.SizeY	Height of the kernel (number of rows)
Kernel.Positive [1]	If true, the center of the kernel is positive
Kernel.Sigma1 [2.0]	Sigma1 of the kernel
Kernel.Sigma2 [1.0]	Sigma2 of the kernel

Gabor kernel Gabor kernel.

Option [default value]	Description
Kernel.SizeX	Width of the kernel (number of columns)
Kernel.SizeY	Height of the kernel (number of rows)
Kernel.Theta	Theta of the kernel
Kernel.Sigma [$\sqrt{2.0}$]	Sigma of the kernel
Kernel.Lambda [10.0]	Lambda of the kernel
Kernel.Psi [$\pi/2.0$]	Psi of the kernel
Kernel.Gamma [0.5]	Gamma of the kernel

FlipTransformation Image flip transformation.

Option [default value]	Description
HorizontalFlip [0]	If true, flip the image horizontally
VerticalFlip [0]	If true, flip the image vertically
RandomHorizontalFlip [0]	If true, randomly flip the image horizontally
RandomVerticalFlip [0]	If true, randomly flip the image vertically

N2D2 IP only **GradientFilterTransformation** Compute image gradient.

Option [default value]	Description
Scale [1.0]	Scale to apply to the computed gradient
Delta [0.0]	Bias to add to the computed gradient
GradientFilter [Sobel]	Filter type to use for computing the gradient. Possible options are: Sobel, Scharr and Laplacian
KernelSize [3]	Size of the filter kernel (has no effect when using the Scharr filter, which kernel size is always 3x3)
ApplyToLabels [0]	If true, use the computed gradient to filter the image label and ignore pixel areas where the gradient is below the Threshold . In this case, only the labels are modified, not the image
InvThreshold [0]	If true, ignored label pixels will be the ones with a low gradient (low contrasted areas)
Threshold [0.5]	Threshold applied on the image gradient
Label []	List of labels to filter (space-separated)
GradientScale [1.0]	Rescale the image by this factor before applying the gradient and the threshold, then scale it back to filter the labels

N2D2 IP only **LabelSliceExtractionTransformation** Extract a slice from an image belonging to a given label.

Option [default value]	Description
Width	Width of the slice to extract
Height	Height of the slice to extract
Label [-1]	Slice should belong to this label ID. If -1, the label ID is random

MagnitudePhaseTransformation Compute the magnitude and phase of a complex two channels input data, with the first channel x being the real part and the second channel y the imaginary part. The resulting data is two channels, the first one with the magnitude and the second one with the phase.

Option [default value]	Description
LogScale [0]	If true, compute the magnitude in log scale

The magnitude is:

$$M_{i,j} = \sqrt{x_{i,j}^2 + x_{i,j}^2}$$

If LogScale = 1, compute $M'_{i,j} = \log(1 + M_{i,j})$.

The phase is:

$$\theta_{i,j} = \text{atan2}(y_{i,j}, x_{i,j})$$

N2D2 IP only MorphologicalReconstructionTransformation Apply a morphological reconstruction transformation to the image. This transformation is also useful for post-processing.

Option [default value]	Description
Operation	Morphological operation to apply. Can be: ReconstructionByErosion: reconstruction by erosion operation ReconstructionByDilation: reconstruction by dilation operation OpeningByReconstruction: opening by reconstruction operation ClosingByReconstruction: closing by reconstruction operation
Size	Size of the structuring element
ApplyToLabels [0]	If true, apply the transformation to the labels instead of the image
Shape [Rectangular]	Shape of the structuring element used for morphology operations. Can be Rectangular, Elliptic or Cross.
NbIterations [1]	Number of times erosion and dilation are applied for opening and closing reconstructions

N2D2 IP only MorphologyTransformation Apply a morphology transformation to the image. This transformation is also useful for post-processing.

Option [default value]	Description
Operation	Morphological operation to apply. Can be: Erode: erode operation ($= \text{erode}(\text{src})$) Dilate: dilate operation ($= \text{dilate}(\text{src})$) Opening: opening operation ($\text{open}(\text{src}) = \text{dilate}(\text{erode}(\text{src}))$) Closing: closing operation ($\text{close}(\text{src}) = \text{erode}(\text{dilate}(\text{src}))$) Gradient: morphological gradient ($= \text{dilate}(\text{src}) - \text{erode}(\text{src})$) TopHat: top hat ($= \text{src} - \text{open}(\text{src})$) BlackHat: black hat ($= \text{close}(\text{src}) - \text{src}$)
Size	Size of the structuring element
ApplyToLabels [0]	If true, apply the transformation to the labels instead of the image
Shape [Rectangular]	Shape of the structuring element used for morphology operations. Can be Rectangular, Elliptic or Cross.
NbIterations [1]	Number of times erosion and dilation are applied

NormalizeTransformation Normalize the image.

Option [default value]	Description
Norm [MinMax]	Norm type, can be: L1: L1 normalization L2: L2 normalization Linf: Linf normalization MinMax: min-max normalization
NormValue [1.0]	Norm value (for L1, L2 and Linf) Such that $\ data\ _{L_p} = NormValue$
NormMin [0.0]	Min value (for MinMax only) Such that $\min(data) = NormMin$
NormMax [1.0]	Max value (for MinMax only) Such that $\max(data) = NormMax$
PerChannel [0]	If true, normalize each channel individually

PadCropTransformation Pad/crop the image to a specified size.

Option [default value]	Description
Width	Width of the padded/cropped image
Height	Height of the padded/cropped image
PaddingBackground [MeanColor]	Background color used when padding. Possible values: MeanColor: pad with the mean color of the image BlackColor: pad with black

N2D2 IP only **RandomAffineTransformation** Apply a global random affine transformation to the values of the image.

Option [default value]	Description
GainVar	Random gain is in range $\pm GainVar$
BiasVar [0.0]	Random bias is in range $\pm BiasVar$

RangeAffineTransformation Apply an affine transformation to the values of the image.

Option [default value]	Description
FirstOperator	First operator, can be Plus, Minus, Multiplies, Divides
FirstValue	First value
SecondOperator [Plus]	Second operator, can be Plus, Minus, Multiplies, Divides
SecondValue [0.0]	Second value

The final operation is the following:

$$f(x) = (x \underset{op_{1st}}{o} val_{1st}) \underset{op_{2nd}}{o} val_{2nd}$$

N2D2 IP only **RangeClippingTransformation** Clip the value range of the image.

Option [default value]	Description
RangeMin [$\min(data)$]	Image values below RangeMin are clipped to 0
RangeMax [$\max(data)$]	Image values above RangeMax are clipped to 1 (or the maximum integer value of the data type)

RescaleTransformation Rescale the image to a specified size.

Option [default value]	Description
Width	Width of the rescaled image
Height	Height of the rescaled image
KeepAspectRatio [0]	If true, keeps the aspect ratio of the image
ResizeToFit [1]	If true, resize along the longest dimension when KeepAspectRatio is true

ReshapeTransformation Reshape the data to a specified size.

Option [default value]	Description
NbRows	New number of rows
NbCols [0]	New number of cols (0 = no check)
NbChannels [0]	New number of channels (0 = no change)

N2D2 IP only **SliceExtractionTransformation** Extract a slice from an image.

Option [default value]	Description
Width	Width of the slice to extract
Height	Height of the slice to extract
OffsetX [0]	X offset of the slice to extract
OffsetY [0]	Y offset of the slice to extract
RandomOffsetX [0]	If true, the X offset is chosen randomly
RandomOffsetY [0]	If true, the Y offset is chosen randomly
AllowPadding [0]	If true, zero-padding is allowed if the image is smaller than the slice to extract

ThresholdTransformation Apply a thresholding transformation to the image. This transformation is also useful for post-processing.

Option [default value]	Description
Threshold	Threshold value
OtsuMethod [0]	Use Otsu's method to determine the optimal threshold (if true, the Threshold value is ignored)
Operation [Binary]	Thresholding operation to apply. Can be: Binary BinaryInverted Truncate ToZero ToZeroInverted
MaxValue [1.0]	Max. value to use with Binary and BinaryInverted operations

TrimTransformation Trim the image.

Option [default value]	Description
NbLevels	Number of levels for the color discretization of the image
Method [Discretize]	Possible values are: Reduce: discretization using K-means Discretize: simple discretization

WallisFilterTransformation Apply Wallis filter to the image.

Option [default value]	Description
Size	Size of the filter
Mean [0.0]	Target mean value
StdDev [1.0]	Target standard deviation
PerChannel [0]	If true, apply Wallis filter to each channel individually (this parameter is meaningful only if Size is 0)

3.5 Network layers

3.5.1 Layer definition

Common set of parameters for any kind of layer.

Option [default value]	Description
Input	Name of the section(s) for the input layer(s). Comma separated
Type	Type of the layer. Can be any of the type described below
Model [DefaultModel]	Layer model to use
ConfigSection []	Name of the configuration section for layer

To specify that the back-propagated error must be computed at the output of a given layer (generally the last layer, or output layer), one must add a target section named *LayerName.Target*:

```
...
[LayerName.Target]
TargetValue=1.0 ; default: 1.0
DefaultValue=0.0 ; default: -1.0
```

3.5.2 Weight fillers

Fillers to initialize weights and biases in the different type of layer.

Usage example:

```
[conv1]
...
WeightsFiller=NormalFiller
WeightsFiller.Mean=0.0
WeightsFiller.StdDev=0.05
...
```

The initial weights distribution for each layer can be checked in the *weights_init* folder, with an example shown in figure 13.

ConstantFiller Fill with a constant value.

Option	Description
<i>FillerName.Value</i>	Value for the filling

NormalFiller Fill with a normal distribution.

Option [default value]	Description
<i>FillerName.Mean</i> [0.0]	Mean value of the distribution
<i>FillerName.StdDev</i> [1.0]	Standard deviation of the distribution




Figure 13: Initial weights distribution of a layer using a normal distribution (**NormalFiller**) with a 0 mean and a 0.05 standard deviation.

UniformFiller Fill with an uniform distribution.

Option [default value]	Description
<i>FillerName</i> .Min [0.0]	Min. value
<i>FillerName</i> .Max [1.0]	Max. value

XavierFiller Fill with an uniform distribution with normalized variance ([Glorot and Bengio, 2010](#)).

Option [default value]	Description
<i>FillerName</i> .VarianceNorm [FanIn]	Normalization, can be FanIn, Average or FanOut
<i>FillerName</i> .Distribution [Uniform]	Distribution, can be Uniform or Normal

Use an uniform distribution with interval $[-scale, scale]$, with $scale = \sqrt{\frac{3.0}{n}}$.

- $n = fan-in$ with FanIn, resulting in $Var(W) = \frac{1}{fan-in}$
- $n = \frac{(fan-in+fan-out)}{2}$ with Average, resulting in $Var(W) = \frac{2}{fan-in+fan-out}$
- $n = fan-out$ with FanOut, resulting in $Var(W) = \frac{1}{fan-out}$

3.5.3 Weight solvers

SGDSolver_Frame SGD Solver for Frame models.

Option [default value]	Description
<i>SolverName</i> .LearningRate [0.01]	Learning rate
<i>SolverName</i> .Momentum [0.0]	Momentum
<i>SolverName</i> .Decay [0.0]	Decay
<i>SolverName</i> .LearningRatePolicy [None]	Learning rate decay policy. Can be any of None, StepDecay, ExponentialDecay, InvTDecay, PolyDecay
<i>SolverName</i> .LearningRateStepSize [1]	Learning rate step size (in number of stimuli)
<i>SolverName</i> .LearningRateDecay [0.1]	Learning rate decay
<i>SolverName</i> .Clamping [0]	If true, clamp the weights and bias between -1 and 1
<i>SolverName</i> .Power [0.0]	Polynomial learning rule power parameter
<i>SolverName</i> .MaxIterations [0.0]	Polynomial learning rule maximum number of iterations

The learning rate decay policies are the following:

- **StepDecay**: every *SolverName*.LearningRateStepSize stimuli, the learning rate is reduced by a factor *SolverName*.LearningRateDecay;
- **ExponentialDecay**: the learning rate is $\alpha = \alpha_0 \exp(-kt)$, with α_0 the initial learning rate *SolverName*.LearningRate, k the rate decay *SolverName*.LearningRateDecay and t the step number (one step every *SolverName*.LearningRateStepSize stimuli);
- **InvTDecay**: the learning rate is $\alpha = \alpha_0 / (1 + kt)$, with α_0 the initial learning rate *SolverName*.LearningRate, k the rate decay *SolverName*.LearningRateDecay and t the step number (one step every *SolverName*.LearningRateStepSize stimuli).
- **InvDecay**: the learning rate is $\alpha = \alpha_0 * (1 + kt)^{-n}$, with α_0 the initial learning rate *SolverName*.LearningRate, k the rate decay *SolverName*.LearningRateDecay, t the current iteration and n the power parameter *SolverName*.Power
- **PolyDecay**: the learning rate is $\alpha = \alpha_0 * (1 - \frac{k}{t})^n$, with α_0 the initial learning rate *SolverName*.LearningRate, k the current iteration, t the maximum number of iteration *SolverName*.MaxIterations and n the power parameter *SolverName*.Power

SGDSolver_Frame_CUDA SGD Solver for Frame_CUDA models.

Option [default value]	Description
<i>SolverName</i> .LearningRate [0.01]	Learning rate
<i>SolverName</i> .Momentum [0.0]	Momentum
<i>SolverName</i> .Decay [0.0]	Decay
<i>SolverName</i> .LearningRatePolicy [None]	Learning rate decay policy. Can be any of None, StepDecay, ExponentialDecay, InvTDecay
<i>SolverName</i> .LearningRateStepSize [1]	Learning rate step size (in number of stimuli)
<i>SolverName</i> .LearningRateDecay [0.1]	Learning rate decay
<i>SolverName</i> .Clamping [0]	If true, clamp the weights and bias between -1 and 1

The learning rate decay policies are identical to the ones in the `SGDSolver_Frame` solver.

3.5.4 Activation functions

Activation function to be used at the output of layers.

Usage example:

```
[conv1]
...
ActivationFunction=Rectifier
ActivationFunction.LeakSlope=0.01
ActivationFunction.Clipping=20
...
```

Logistic Logistic activation function.

LogisticWithLoss Logistic with loss activation function.

Rectifier Rectifier or ReLU activation function.

Option [default value]	Description
<code>ActivationFunction.LeakSlope</code> [0.0]	Leak slope for negative inputs
<code>ActivationFunction.Clipping</code> [0.0]	Clipping value for positive outputs

Saturation Saturation activation function.

Softplus Softplus activation function.

Tanh Tanh activation function.

Computes $y = \tanh(\alpha x)$.

Option [default value]	Description
<code>ActivationFunction.Alpha</code> [1.0]	α parameter

TanhLeCun Tanh activation function with an α parameter of $1.7159 \times (2.0/3.0)$.

3.5.5 Conv

Convolutional layer.

Option [default value]	Description
<code>KernelWidth</code>	Width of the kernel
<code>KernelHeight</code>	Height of the kernel
<code>NbChannels</code>	Number of output channels
<code>SubSampleX</code> [1]	X-axis subsampling factor of the output feature maps
<code>SubSampleY</code> [1]	Y-axis subsampling factor of the output feature maps
<code>SubSample</code> [1]	Subsampling factor of the output feature maps (mutually exclusive with <code>SubSampleX</code> and <code>SubSampleY</code>)
<code>StrideX</code> [1]	X-axis stride of the kernels
<code>StrideY</code> [1]	Y-axis stride of the kernels

Stride [1]	Stride of the kernels (mutually exclusive with StrideX and StrideY)
PaddingX [0]	X-axis input padding
PaddingY [0]	Y-axis input padding
Padding [0]	Input padding (mutually exclusive with PaddingX and PaddingY)
ActivationFunction [Tanh]	Activation function. Can be any of Logistic, LogisticWithLoss, Rectifier, Softplus, TanhLeCun, Linear, Saturation Or Tanh
WeightsFiller [NormalFiller(0.0, 0.05)]	Weights initial values filler
BiasFiller [NormalFiller(0.0, 0.05)]	Biases initial values filler
Mapping.SizeX [1]	Mapping canvas pattern default width
Mapping.SizeY [1]	Mapping canvas pattern default height
Mapping.Size [1]	Mapping canvas pattern default size (mutually exclusive with Mapping.SizeX and Mapping.SizeY)
Mapping.StrideX [1]	Mapping canvas default X-axis step
Mapping.StrideY [1]	Mapping canvas default Y-axis step
Mapping.Stride [1]	Mapping canvas default step (mutually exclusive with Mapping.StrideX and Mapping.StrideY)
Mapping.OffsetX [0]	Mapping canvas default X-axis offset
Mapping.OffsetY [0]	Mapping canvas default Y-axis offset
Mapping.Offset [0]	Mapping canvas default offset (mutually exclusive with Mapping.OffsetX and Mapping.OffsetY)
Mapping.NbIterations [0]	Mapping canvas pattern default number of iterations (0 means no limit)
Mapping(in).SizeX [1]	Mapping canvas pattern default width for input layer in
Mapping(in).SizeY [1]	Mapping canvas pattern default height for input layer in
Mapping(in).Size [1]	Mapping canvas pattern default size for input layer in (mutually exclusive with Mapping(in).SizeX and Mapping(in).SizeY)
Mapping(in).StrideX [1]	Mapping canvas default X-axis step for input layer in
Mapping(in).StrideY [1]	Mapping canvas default Y-axis step for input layer in
Mapping(in).Stride [1]	Mapping canvas default step for input layer in (mutually exclusive with Mapping(in).StrideX and Mapping(in).StrideY)
Mapping(in).OffsetX [0]	Mapping canvas default X-axis offset for input layer in
Mapping(in).OffsetY [0]	Mapping canvas default Y-axis offset for input layer in
Mapping(in).Offset [0]	Mapping canvas default offset for input layer in (mutually exclusive with Mapping(in).OffsetX and Mapping(in).OffsetY)
Mapping(in).NbIterations [0]	Mapping canvas pattern default number of iterations for input layer in (0 means no limit)

Configuration parameters (*Frame* models)

Option [default value]	Model(s)	Description
NoBias [1]	<i>all Frame</i>	If true, don't use bias
Solvers.*	<i>all Frame</i>	Any solver parameters

WeightsSolver.*	<i>all Frame</i>	Weights solver parameters, take precedence over the Solvers.* parameters
BiasSolver.*	<i>all Frame</i>	Bias solver parameters, take precedence over the Solvers.* parameters

Configuration parameters (*Spike* models)

Experimental option (implementation may be wrong or susceptible to change)

Option [default value]	Model(s)	Description
IncomingDelay [1 TimePs ;100 TimeFs]	<i>all Spike</i>	Synaptic incoming delay w_{delay}
Threshold [1.0]	Spike, Spike_RRAM	Threshold of the neuron I_{thres}
BipolarThreshold [1]	Spike, Spike_RRAM	If true, the threshold is also applied to the absolute value of negative values (generating negative spikes)
Leak [0.0]	Spike, Spike_RRAM	Neural leak time constant τ_{leak} (if 0, no leak)
Refractory [0.0]	Spike, Spike_RRAM	Neural refractory period T_{refrac}
WeightsRelInit [0.0;0.05]	Spike	Relative initial synaptic weight w_{init}
WeightsMinMean [1;0.1]	Spike_RRAM	Mean minimum synaptic weight w_{min}
WeightsMaxMean [100;10.0]	Spike_RRAM	Mean maximum synaptic weight w_{max}
WeightsMinVarSlope [0.0]	Spike_RRAM	OxRAM specific parameter
WeightsMinVarOrigin [0.0]	Spike_RRAM	OxRAM specific parameter
WeightsMaxVarSlope [0.0]	Spike_RRAM	OxRAM specific parameter
WeightsMaxVarOrigin [0.0]	Spike_RRAM	OxRAM specific parameter
WeightsSetProba [1.0]	Spike_RRAM	Intrinsic SET switching probability P_{SET} (upon receiving a SET programming pulse). Assuming uniform statistical distribution (not well supported by experiments on RRAM)
WeightsResetProba [1.0]	Spike_RRAM	Intrinsic RESET switching probability P_{RESET} (upon receiving a RESET programming pulse). Assuming uniform statistical distribution (not well supported by experiments on RRAM)
SynapticRedundancy [1]	Spike_RRAM	Synaptic redundancy (number of RRAM device per synapse)
BipolarWeights [0]	Spike_RRAM	Bipolar weights
BipolarIntegration [0]	Spike_RRAM	Bipolar integration
LtpProba [0.2]	Spike_RRAM	Extrinsic STDP LTP probability (cumulative with intrinsic SET switching probability P_{SET})
LtdProba [0.1]	Spike_RRAM	Extrinsic STDP LTD probability (cumulative with intrinsic RESET switching probability P_{RESET})
Stdpltp [1000 TimePs]	Spike_RRAM	STDP LTP time window T_{LTP}
InhibitRefractory [0 TimePs]	Spike_RRAM	Neural lateral inhibition period $T_{inhibit}$
EnableStdpl [1]	Spike_RRAM	If false, STDP is disabled (no synaptic weight change)
RefractoryIntegration [1]	Spike_RRAM	If true, reset the integration to 0 during the refractory period
DigitalIntegration [0]	Spike_RRAM	If false, the analog value of the devices is integrated, instead of their binary value

3.5.6 Deconv

Deconvolutionlayer.

Option [default value]	Description
KernelWidth	Width of the kernel
KernelHeight	Height of the kernel
NbChannels	Number of output channels
StrideX [1]	X-axis stride of the kernels
StrideY [1]	Y-axis stride of the kernels
Stride [1]	Stride of the kernels (mutually exclusive with StrideX and StrideY)
PaddingX [0]	X-axis input padding
PaddingY [0]	Y-axis input padding
Padding [0]	Input padding (mutually exclusive with PaddingX and PaddingY)
ActivationFunction [Tanh]	Activation function. Can be any of Logistic, LogisticWithLoss, Rectifier, Softplus, TanhLeCun, Linear, Saturation Or Tanh
WeightsFiller [NormalFiller(0.0, 0.05)]	Weights initial values filler
BiasFiller [NormalFiller(0.0, 0.05)]	Biases initial values filler
Mapping.SizeX [1]	Mapping canvas pattern default width
Mapping.SizeY [1]	Mapping canvas pattern default height
Mapping.Size [1]	Mapping canvas pattern default size (mutually exclusive with Mapping.SizeX and Mapping.SizeY)
Mapping.StrideX [1]	Mapping canvas default X-axis step
Mapping.StrideY [1]	Mapping canvas default Y-axis step
Mapping.Stride [1]	Mapping canvas default step (mutually exclusive with Mapping.StrideX and Mapping.StrideY)
Mapping.OffsetX [0]	Mapping canvas default X-axis offset
Mapping.OffsetY [0]	Mapping canvas default Y-axis offset
Mapping.Offset [0]	Mapping canvas default offset (mutually exclusive with Mapping.OffsetX and Mapping.OffsetY)
Mapping.NbIterations [0]	Mapping canvas pattern default number of iterations (0 means no limit)
Mapping(in).SizeX [1]	Mapping canvas pattern default width for input layer in
Mapping(in).SizeY [1]	Mapping canvas pattern default height for input layer in
Mapping(in).Size [1]	Mapping canvas pattern default size for input layer in (mutually exclusive with Mapping(in).SizeX and Mapping(in).SizeY)
Mapping(in).StrideX [1]	Mapping canvas default X-axis step for input layer in
Mapping(in).StrideY [1]	Mapping canvas default Y-axis step for input layer in
Mapping(in).Stride [1]	Mapping canvas default step for input layer in (mutually exclusive with Mapping(in).StrideX and Mapping(in).StrideY)
Mapping(in).OffsetX [0]	Mapping canvas default X-axis offset for input layer in
Mapping(in).OffsetY [0]	Mapping canvas default Y-axis offset for input layer in
Mapping(in).Offset [0]	Mapping canvas default offset for input layer in (mutually exclusive with Mapping(in).OffsetX and

Mapping(in).NbIterations [0]	Mapping(in).OffsetY Mapping canvas pattern default number of iterations for input layer in (0 means no limit)
------------------------------	--

Configuration parameters (*Frame* models)

Option [default value]	Model(s)	Description
NoBias [1]	<i>all Frame</i>	If true, don't use bias
BackPropagate [1]	<i>all Frame</i>	If true, enable backpropagation
Solvers.*	<i>all Frame</i>	Any solver parameters
WeightsSolver.*	<i>all Frame</i>	Weights solver parameters, take precedence over the Solvers.* parameters
BiasSolver.*	<i>all Frame</i>	Bias solver parameters, take precedence over the Solvers.* parameters

3.5.7 Pool

Pooling layer.

Option [default value]	Description
PoolWidth	Width of the pooling area
PoolHeight	Height of the pooling area
NbChannels	Number of output channels
StrideX [1]	X-axis stride of the pooling areas
StrideY [1]	Y-axis stride of the pooling areas
Stride [1]	Stride of the pooling areas (mutually exclusive with StrideX and StrideY)
PaddingX [0]	X-axis input padding
PaddingY [0]	Y-axis input padding
Padding [0]	Input padding
ActivationFunction [Linear]	Activation function. Can be any of Logistic, LogisticWithLoss, Rectifier, Softplus, TanhLeCun, Linear, Saturation OR Tanh
Mapping.SizeX [1]	Mapping canvas pattern default width
Mapping.SizeY [1]	Mapping canvas pattern default height
Mapping.Size [1]	Mapping canvas pattern default size (mutually exclusive with Mapping.SizeX and Mapping.SizeY)
Mapping.StrideX [1]	Mapping canvas default X-axis step
Mapping.StrideY [1]	Mapping canvas default Y-axis step
Mapping.Stride [1]	Mapping canvas default step (mutually exclusive with Mapping.StrideX and Mapping.StrideY)
Mapping.OffsetX [0]	Mapping canvas default X-axis offset
Mapping.OffsetY [0]	Mapping canvas default Y-axis offset
Mapping.Offset [0]	Mapping canvas default offset (mutually exclusive with Mapping.OffsetX and Mapping.OffsetY)
Mapping.NbIterations [0]	Mapping canvas pattern default number of iterations (0 means no limit)
Mapping(in).SizeX [1]	Mapping canvas pattern default width for input layer in

Mapping(in).SizeY [1] Mapping(in).Size [1]	Mapping canvas pattern default height for input layer in Mapping canvas pattern default size for input layer in (mutually exclusive with Mapping(in).SizeX and Mapping(in).SizeY)
Mapping(in).StrideX [1] Mapping(in).StrideY [1] Mapping(in).Stride [1]	Mapping canvas default X-axis step for input layer in Mapping canvas default Y-axis step for input layer in Mapping canvas default step for input layer in (mutually exclusive with Mapping(in).StrideX and Mapping(in).StrideY)
Mapping(in).OffsetX [0] Mapping(in).OffsetY [0] Mapping(in).Offset [0]	Mapping canvas default X-axis offset for input layer in Mapping canvas default Y-axis offset for input layer in Mapping canvas default offset for input layer in (mutually exclusive with Mapping(in).OffsetX and Mapping(in).OffsetY)
Mapping(in).NbIterations [0]	Mapping canvas pattern default number of iterations for input layer in (0 means no limit)

Configuration parameters (*Spike* models)

Option [default value]	Model(s)	Description
IncomingDelay [1 TimePs ;100 TimeFs] value	<i>all Spike</i>	Synaptic incoming delay w_{delay}

3.5.8 FMP

Fractional max pooling layer (Graham, 2014).

Option [default value]	Description
NbChannels	Number of output channels
ScalingRatio	Scaling ratio. The output size is $round\left(\frac{\text{input size}}{\text{scaling ratio}}\right)$.
ActivationFunction [Linear]	Activation function. Can be any of Logistic, LogisticWithLoss, Rectifier, Softplus, TanhLeCun, Linear, Saturation OR Tanh

Configuration parameters (*Frame* models)

Option [default value]	Model(s)	Description
Overlapping [1]	<i>all Frame</i>	If true, use overlapping regions, else use disjoint regions
PseudoRandom [1]	<i>all Frame</i>	If true, use pseudorandom sequences, else use random sequences

3.5.9 Fc

Fully connected layer.

Option [default value]	Description
NbOutputs	Number of output neurons
WeightsFiller [NormalFiller(0.0, 0.05)]	Weights initial values filler
BiasFiller [NormalFiller(0.0, 0.05)]	Biases initial values filler

Configuration parameters (*Frame* models)

Option [default value]	Model(s)	Description
NoBias [1]	<i>all Frame</i>	If true, don't use bias
BackPropagate [1]	<i>all Frame</i>	If true, enable backpropagation
Solvers.*	<i>all Frame</i>	Any solver parameters
WeightsSolver.*	<i>all Frame</i>	Weights solver parameters, take precedence over the Solvers.* parameters
BiasSolver.*	<i>all Frame</i>	Bias solver parameters, take precedence over the Solvers.* parameters
DropConnect [1.0]	Frame	If below 1.0, fraction of synapses that are disabled with drop connect

Configuration parameters (*Spike* models)

Option [default value]	Model(s)	Description
IncomingDelay [1 TimePs ;100 TimeFs]	<i>all Spike</i>	Synaptic incoming delay w_{delay}
Threshold [1.0]	Spike, Spike_RRAM	Threshold of the neuron I_{thres}
BipolarThreshold [1]	Spike, Spike_RRAM	If true, the threshold is also applied to the absolute value of negative values (generating negative spikes)
Leak [0.0]	Spike, Spike_RRAM	Neural leak time constant τ_{leak} (if 0, no leak)
Refractory [0.0]	Spike, Spike_RRAM	Neural refractory period T_{refrac}
TerminateDelta [0]	Spike, Spike_RRAM	Terminate delta
WeightsRelInit [0.0;0.05]	Spike	Relative initial synaptic weight w_{init}
WeightsMinMean [1;0.1]	Spike_RRAM	Mean minimum synaptic weight w_{min}
WeightsMaxMean [100;10.0]	Spike_RRAM	Mean maximum synaptic weight w_{max}
WeightsMinVarSlope [0.0]	Spike_RRAM	OxRAM specific parameter
WeightsMinVarOrigin [0.0]	Spike_RRAM	OxRAM specific parameter
WeightsMaxVarSlope [0.0]	Spike_RRAM	OxRAM specific parameter
WeightsMaxVarOrigin [0.0]	Spike_RRAM	OxRAM specific parameter
WeightsSetProba [1.0]	Spike_RRAM	Intrinsic SET switching probability P_{SET} (upon receiving a SET programming pulse). Assuming uniform statistical distribution (not well supported by experiments on RRAM)

WeightsResetProba [1.0]	Spike_RRAM	Intrinsic RESET switching probability P_{RESET} (upon receiving a RESET programming pulse). Assuming uniform statistical distribution (not well supported by experiments on RRAM)
SynapticRedundancy [1]	Spike_RRAM	Synaptic redundancy (number of RRAM device per synapse)
BipolarWeights [0]	Spike_RRAM	Bipolar weights
BipolarIntegration [0]	Spike_RRAM	Bipolar integration
LtpProba [0.2]	Spike_RRAM	Extrinsic STDP LTP probability (cumulative with intrinsic SET switching probability P_{SET})
LtdProba [0.1]	Spike_RRAM	Extrinsic STDP LTD probability (cumulative with intrinsic RESET switching probability P_{RESET})
Stdpltp [1000 TimePs]	Spike_RRAM	STDP LTP time window T_{LTP}
InhibitRefractory [0 TimePs]	Spike_RRAM	Neural lateral inhibition period $T_{inhibit}$
EnableStdpl [1]	Spike_RRAM	If false, STDP is disabled (no synaptic weight change)
RefractoryIntegration [1]	Spike_RRAM	If true, reset the integration to 0 during the refractory period
DigitalIntegration [0]	Spike_RRAM	If false, the analog value of the devices is integrated, instead of their binary value

N2D2 IP only 3.5.10 Rbf

Radial basis function fully connected layer.

Option [default value]	Description
NbOutputs	Number of output neurons
CentersFiller [NormalFiller(0.5, 0.05)]	Centers initial values filler
ScalingFiller [NormalFiller(10.0, 0.05)]	Scaling initial values filler

Configuration parameters (*Frame* models)

Option [default value]	Model(s)	Description
Solvers.*	<i>all Frame</i>	Any solver parameters
CentersSolver.*	<i>all Frame</i>	Centers solver parameters, take precedence over the Solvers.* parameters
ScalingSolver.*	<i>all Frame</i>	Scaling solver parameters, take precedence over the Solvers.* parameters
RbfApprox [None]	Frame	Approximation for the Gaussian function, can be any of: None, Rectangular or SemiLinear

3.5.11 Softmax

Softmax layer.

Option [default value]	Description
NbOutputs	Number of output neurons
WithLoss [0]	Softmax followed with a multinomial logistic layer

The softmax function performs the following operation, with $a_{x,y}^i$ and $b_{x,y}^i$ the input and the output respectively at position (x, y) on channel i :

$$b_{x,y}^i = \frac{\exp(a_{x,y}^i)}{\sum_{j=0}^N \exp(a_{x,y}^j)}$$

and

$$da_{x,y}^i = \sum_{j=0}^N (\delta_{ij} - a_{x,y}^i) a_{x,y}^j db_{x,y}^j$$

When the `WithLoss` option is enabled, compute the gradient directly in respect of the cross-entropy loss:

$$L_{x,y} = \sum_{j=0}^N t_{x,y}^j \log(b_{x,y}^j)$$

In this case, the gradient output becomes:

$$da_{x,y}^i = db_{x,y}^i$$

with

$$db_{x,y}^i = t_{x,y}^i - b_{x,y}^i$$

3.5.12 LRN

Local Response Normalization (LRN) layer.

Option [default value]	Description
NbOutputs	Number of output neurons

The response-normalized activity $b_{x,y}^i$ is given by the expression:

$$b_{x,y}^i = \frac{a_{x,y}^i}{\left(k + \alpha \sum_{j=\max(0, i-n/2)}^{\min(N-1, i+n/2)} (a_{x,y}^j)^2 \right)^\beta}$$

Configuration parameters (*Frame* models)

Option [default value]	Model(s)	Description
N [5]	all Frame	Normalization window width in elements
Alpha [1.0e-4]	all Frame	Value of the alpha variance scaling parameter in the normalization formula
Beta [0.75]	all Frame	Value of the beta power parameter in the normalization formula
K [2.0]	all Frame	Value of the k parameter in normalization formula

3.5.13 Dropout

Dropout layer ([Srivastava et al., 2012](#)).

Option [default value]	Description
NbOutputs	Number of output neurons

Configuration parameters (*Frame* models)

Option [default value]	Model(s)	Description
Dropout [0.5]	Frame_CUDA	The probability with which the value from input would be dropped

3.5.14 BatchNorm

Batch Normalization layer ([Ioffe and Szegedy, 2015](#)).

Option [default value]	Description
NbOutputs	Number of output neurons
ActivationFunction [Tanh]	Activation function. Can be any of Logistic, LogisticWithLoss, Rectifier, Softplus, TanhLeCun, Linear, Saturation Or Tanh

Configuration parameters (*Frame* models)

Option [default value]	Model(s)	Description
Solvers.*	all Frame	Any solver parameters
ScaleSolver.*	all Frame	Scale solver parameters, take precedence over the Solvers.* parameters
BiasSolver.*	all Frame	Bias solver parameters, take precedence over the Solvers.* parameters
Epsilon [0.0]	all Frame	Epsilon value used in the batch normalization formula. If 0.0, automatically choose the minimum possible value.

3.5.15 Transformation

Transformation layer, which can apply any transformation described in 3.4.1. Useful for fully CNN post-processing for example.

Option [default value]	Description
NbOutputs	Number of outputs
Transformation	Name of the transformation to apply

The Transformation options must be placed in the same section.

Usage example for fully CNNs:

```
[post.Transformation-thres]
Input=... ; for example, network's logistic of softmax output layer
NbOutputs=1
Type=Transformation
Transformation=ThresholdTransformation
Operation=ToZero
Threshold=0.75

[post.Transformation-morpho]
Input=post.Transformation-thres
NbOutputs=1
Type=Transformation
Transformation=MorphologyTransformation
Operation=Opening
Size=3
```

4 Tutorials

4.1 Building a classifier neural network

For this tutorial, we will use the classical MNIST handwritten digit dataset. A driver module already exists for this dataset, named `MNIST_IDX_Database`.

To instantiate it, just add the following lines in a new INI file:

```
[database]
Type=MNIST_IDX_Database
Validation=0.2 ; Use 20% of the dataset for validation
```

In order to create a neural network, we first need to define its input, which is declared with a `[sp]` section (*sp* for *StimuliProvider*). In this section, we configure the size of the input and the batch size:

```
[sp]
SizeX=32
SizeY=32
BatchSize=128
```

We can also add pre-processing transformations to the *StimuliProvider*, knowing that the final data size after transformations must match the size declared in the `[sp]` section. Here, we must rescale the MNIST 28x28 images to match the 32x32 network input size.

```
[sp.Transformation_1]
Type=RescaleTransformation
Width=[sp]SizeX
Height=[sp]SizeY
```

Next, we declare the neural network layers. In this example, we reproduced the well-known LeNet network. The first layer is a 5x5 convolutional layer, with 6 channels. Since there is only one input channel, there will be only 6 convolution kernels in this layer.

```
[conv1]
Input=sp
Type=Conv
KernelWidth=5
KernelHeight=5
NbChannels=6
```

The next layer is a 2x2 MAX pooling layer, with a stride of 2 (non-overlapping MAX pooling).

```
[pool1]
Input=conv1
Type=Pool
PoolWidth=2
PoolHeight=2
NbChannels=[conv1]NbChannels
Stride=2
Pooling=Max
Mapping.Size=1 ; One to one connection between input and output channels
```

The next layer is a 5x5 convolutional layer with 16 channels.

```
[conv2]
Input=pool1
Type=Conv
KernelWidth=5
KernelHeight=5
NbChannels=16
```

Note that in LeNet, the `[conv2]` layer is not fully connected to the pooling layer. In N2D2, a custom mapping can be defined for each input connection. The connection of n -th output map to the inputs is defined by the n -th column of the matrix below, where the rows correspond to the inputs.

```

Map(pool1)=\
1 0 0 0 1 1 1 0 0 1 1 1 1 0 1 1 \
1 1 0 0 0 1 1 1 0 0 1 1 1 1 0 1 \
1 1 1 0 0 0 1 1 1 0 0 1 0 1 1 1 \
0 1 1 1 0 0 1 1 1 1 0 0 1 0 1 1 \
0 0 1 1 1 0 0 1 1 1 1 0 1 1 0 1 \
0 0 0 1 1 1 0 0 1 1 1 1 0 1 1 1

```

Another MAX pooling and convolution layer follow:

```

[pool2]
Input=conv2
Type=Pool
PoolWidth=2
PoolHeight=2
NbChannels=[conv2]NbChannels
Stride=2
Pooling=Max
Mapping.Size=1

[conv3]
Input=pool2
Type=Conv
KernelWidth=5
KernelHeight=5
NbChannels=120

```

The network is composed of two fully-connected layers of 84 and 10 neurons respectively:

```

[fc1]
Input=conv3
Type=Fc
NbOutputs=84

[fc2]
Input=fc1
Type=Fc
NbOutputs=10

```

Finally, we use a softmax layer to obtain output classification probabilities and compute the loss function.

```

[softmax]
Input=fc2
Type=Softmax
NbOutputs=[fc2]NbOutputs
WithLoss=1

```

In order to tell N2D2 to compute the error and the classification score on this softmax layer, one must attach a N2D2 *Target* to this layer, with a section with the same name suffixed with *.Target*:

```

[softmax.Target]

```

By default, the activation function for the convolution and the fully-connected layers is the hyperbolic tangent. Because the [fc2] layer is fed to a softmax, it should not have any activation function. We can specify it by adding the following line in the [fc2] section:

```

[fc2]
...
ActivationFunction=Linear

```

In order to improve further the networks performances, several things can be done:

- **Use ReLU activation functions.** In order to do so, just add the following in the [conv1], [conv2], [conv3] and [fc1] layer sections:

```

ActivationFunction=Rectifier

```

For the ReLU activation function to be effective, the weights must be initialized carefully, in order to avoid dead units that would be stuck in the $]-\infty, 0]$ output range before the ReLU function. In N2D2, one can use a custom `WeightsFiller` for the weights initialization. For the ReLU activation function, a popular and efficient filler is the so-called `XavierFiller` (see the 3.5.2 section for more information):

```
WeightsFiller=XavierFiller
```

- **Use dropout layers.** Dropout is highly effective to improve the network generalization capacity. Here is an example of a dropout layer inserted between the `[fc1]` and `[fc2]` layers:

```
[fc1]
...

[fc1.drop]
Input=fc1
Type=Dropout
NbOutputs=[fc1]NbOutputs

[fc2]
Input=fc1.drop ; Replaces "Input=fc1"
...
```

- **Tune the learning parameters.** You may want to tune the learning rate and other learning parameters depending on the learning problem at hand. In order to do so, you can add a configuration section that can be common (or not) to all the layers. Here is an example of configuration section:

```
[conv1]
...
ConfigSection=common.config

[...]
...

[common.config]
NoBias=1
WeightsSolver.LearningRate=0.05
WeightsSolver.Decay=0.0005
Solvers.LearningRatePolicy=StepDecay
Solvers.LearningRateStepSize=[sp]_EpochSize
Solvers.LearningRateDecay=0.993
Solvers.Clamping=1
```

For more details on the configuration parameters for the `Solver`, see section 3.5.3.

- **Add input distortion.** See for example the `DistortionTransformation` (section 3.4.1).

The complete INI model file corresponding to this tutorial can be found in the *models* directory of N2D2.

In order to use CUDA/GPU accelerated learning, the default layer model should be switched to `Frame_CUDA`. You can enable this model by adding the following line at the top of the INI file (before the first section):

```
DefaultModel=Frame_CUDA
```

4.2 Building a segmentation neural network

In this tutorial, we will learn how to do image segmentation with N2D2. As an example, we will implement a face detection and gender recognition neural network, using the IMDB-WIKI dataset.

First, we need to instantiate the IMDB-WIKI dataset built-in N2D2 driver:

```
[database]
Type=IMDBWIKI_Database
WikiSet=1 ; Use the WIKI part of the dataset
IMDBSet=0 ; Don't use the IMDB part (less accurate annotation)
Learn=0.90
Validation=0.05
DefaultLabel=background ; Label for pixels outside any ROI (default is no label, pixels are
                        ignored)
```

We must specify a default label for the background, because we want to learn to differentiate faces from the background (and not simply ignore the background for the learning).

The network input is then declared:

```
[sp]
SizeX=480
SizeY=360
BatchSize=48
CompositeStimuli=1
```

In order to work with segmented data, i.e. data with bounding box annotations or pixel-wise annotations (as opposed to a single label per data), one must enable the `CompositeStimuli` option in the `[sp]` section.

We can then perform various operations on the data before feeding it to the network, like for example converting the 3-channels RGB input images to single-channel gray images:

```
[sp.Transformation-1]
Type=ChannelExtractionTransformation
CSChannel=Gray
```

We must only rescale the images to match the networks input size. This can be done using a `RescaleTransformation`, followed by a `PadCropTransformation` if one want to keep the images aspect ratio.

```
[sp.Transformation-2]
Type=RescaleTransformation
Width=[sp]SizeX
Height=[sp]SizeY
KeepAspectRatio=1 ; Keep images aspect ratio

; Required to ensure all the images are the same size
[sp.Transformation-3]
Type=PadCropTransformation
Width=[sp]SizeX
Height=[sp]SizeY
```

A common additional operation to extend the learning set is to apply random horizontal mirror to images. This can be achieved with the following `FlipTransformation`:

```
[sp.OnTheFlyTransformation-4]
Type=FlipTransformation
RandomHorizontalFlip=1
ApplyTo=LearnOnly ; Apply this transformation only on the learning set
```

Note that this is an *on-the-fly* transformation, meaning it cannot be cached and is re-executed every time even for the same stimuli. We also apply this transformation only on the learning set, with the `ApplyTo` option.

Next, the neural network can be described:

```
[conv1.1]
Input=sp
Type=Conv
...

[pool11]
...
```

```
[...]
...

[fc2]
Input=drop1
Type=Conv
...

[drop2]
Input=fc2
Type=Dropout
NbOutputs=[fc2]NbChannels
```

A full network description can be found in the *IMDBWIKI.ini* file in the *models* directory of N2D2. It is a fully-CNN network.

Here we will focus on the output layers required to detect the faces and classify their gender. We start from the [drop2] layer, which has 128 channels of size 60x45.

4.2.1 Faces detection

We want to first add an output stage for the faces detection. It is a 1x1 convolutional layer with a single 60x45 output map. For each output pixel, this layer outputs the probability that the pixel belongs to a face.

```
[fc3.face]
Input=drop2
Type=Conv
KernelWidth=1
KernelHeight=1
NbChannels=1
Stride=1
ActivationFunction=LogisticWithLoss
WeightsFiller=XavierFiller
ConfigSection=common.config ; Same solver options that the other layers
```

In order to do so, the activation function of this layer must be of type `LogisticWithLoss`.

We must also tell N2D2 to compute the error and the classification score on this softmax layer, by attaching a N2D2 *Target* to this layer, with a section with the same name suffixed with *.Target*:

```
[fc3.face.Target]
LabelsMapping=${N2D2_MODELS}/IMDBWIKI_target_face.dat
; Visualization parameters
NoDisplayLabel=0
LabelsHueOffset=90
```

In this *Target*, we must specify how the dataset annotations are mapped to the layer's output. This can be done in a separate file using the `LabelsMapping` parameter. Here, since the output layer has a single output per pixel, the target value can only be 0 or 1. A target value of -1 means that this output is ignored (no error back-propagated). Since the only annotations in the IMDB-WIKI dataset are faces, the mapping described in the *IMDBWIKI_target_face.dat* file is easy:

```
# background
background 0

# padding (*) is ignored (-1)
* -1

# not background = face
default 1
```

4.2.2 Gender recognition

We can also add a second output stage for gender recognition. Like before, it would be a 1x1 convolutional layer with a single 60x45 output map. But here, for each output pixel, this layer would output the probability that the pixel represents a female face.

```
[fc3.gender]
Input=drop2
Type=Conv
KernelWidth=1
KernelHeight=1
NbChannels=1
Stride=1
ActivationFunction=LogisticWithLoss
WeightsFiller=XavierFiller
ConfigSection=common.config
```

The output layer is therefore identical to the face's output layer, but the target mapping is different. For the target mapping, the idea is simply to ignore all pixels not belonging to a face and affect the target 0 to male pixels and the target 1 to female pixels.

```
[fc3.gender.Target]
LabelsMapping=${N2D2_MODELS}/IMDBWIKI_target_gender.dat
; Only display gender probability for pixels detected as face pixels
MaskLabelTarget=fc3.face.Target
MaskedLabel=1
```

The content of the *IMDBWIKI_target_gender.dat* file would therefore look like:

```
# background
# ?-* (unknown gender)
# padding
default -1

# male gender
M-? 0 # unknown age
M-0 0
M-1 0
M-2 0
...
M-98 0
M-99 0

# female gender
F-? 1 # unknown age
F-0 1
F-1 1
F-2 1
...
F-98 1
F-99 1
```

4.2.3 ROIs extraction

The next step would be to extract detected face ROIs and assign for each ROI the most probable gender. To this end, we can first set a detection threshold, in terms of probability, to select face pixels. In the following, the threshold is fixed to 75% face probability:

```
[post.Transformation-thres]
Input=fc3.face
Type=Transformation
NbOutputs=1
Transformation=ThresholdTransformation
Operation=ToZero
Threshold=0.75
```

We can then assign a target of type `TargetROIs` to this layer that will automatically create the bounding box using a segmentation algorithm.

```
[post.Transformation-thres.Target-face]
Type=TargetROIs
MinOverlap=0.33 ; Min. overlap fraction to match the ROI to an annotation
FilterMinWidth=5 ; Min. ROI width
FilterMinHeight=5 ; Min. ROI height
FilterMinAspectRatio=0.5 ; Min. ROI aspect ratio
FilterMaxAspectRatio=1.5 ; Max. ROI aspect ratio
LabelsMapping=${N2D2_MODELS}/IMDBWIKI_target_face.dat
```

In order to assign a gender to the extracted ROIs, the above target must be modified to:

```
[post.Transformation-thres.Target-gender]
Type=TargetROIs
ROIsLabelTarget=fc3.gender.Target
MinOverlap=0.33
FilterMinWidth=5
FilterMinHeight=5
FilterMinAspectRatio=0.5
FilterMaxAspectRatio=1.5
LabelsMapping=${N2D2_MODELS}/IMDBWIKI_target_gender.dat
```

Here, we use the `fc3.gender.Target` target to determine the most probable gender of the ROI.

References

- P. Dollár, C. Wojek, B. Schiele, and P. Perona. Pedestrian detection: A benchmark. In *CVPR*, 2009.
- L. Fei-Fei, R. Fergus, and P. Perona. Learning generative visual models from few training examples: an incremental bayesian approach tested on 101 object categories. In *IEEE. CVPR 2004, Workshop on Generative-Model Based Vision*, 2004.
- X. Glorot and Y. Bengio. Understanding the difficulty of training deep feedforward neural networks. In *International conference on artificial intelligence and statistics*, page 249–256, 2010.
- B. Graham. Fractional max-pooling. *CoRR*, abs/1412.6071, 2014.
- G. Griffin, A. Holub, and P. Perona. Caltech-256 object category dataset, 2007.
- S. Houben, J. Stallkamp, J. Salmen, M. Schlipsing, and C. Igel. Detection of traffic signs in real-world images: The German Traffic Sign Detection Benchmark. In *International Joint Conference on Neural Networks*, number 1288, 2013.
- S. Ioffe and C. Szegedy. Batch normalization: Accelerating deep network training by reducing internal covariate shift. *CoRR*, abs/1502.03167, 2015.
- V. Jain and E. Learned-Miller. Fddb: A benchmark for face detection in unconstrained settings, 2010.
- A. Krizhevsky. Learning multiple layers of features from tiny images, 2009.
- Y. LeCun, L. Bottou, Y. Bengio, and P. Haffner. Gradient-based learning applied to document recognition. In *Proceedings of the IEEE*, volume 86, pages 2278–2324, 1998.
- P. Lucey, J. F. Cohn, T. Kanade, J. Saragih, Z. Ambadar, and I. Matthews. The Extended Cohn-Kanade Dataset (CK+): A complete dataset for action unit and emotion-specified expression. 2010.
- A. Rakotomamonjy and G. Gasso. Histogram of gradients of time-frequency representations for audio scene detection, 2014.
- O. Russakovsky, J. Deng, H. Su, J. Krause, S. Satheesh, S. Ma, Z. Huang, A. Karpathy, A. Khosla, M. Bernstein, A. C. Berg, and L. Fei-Fei. ImageNet Large Scale Visual Recognition Challenge. *International Journal of Computer Vision (IJCV)*, 115(3):211–252, 2015. doi: 10.1007/s11263-015-0816-y.
- N. Srivastava, G. Hinton, A. Krizhevsky, I. Sutskever, and R. Salakhutdinov. Dropout: A simple way to prevent neural networks from overfitting. *Journal of Machine Learning Research*, 15: 1929–1958, 2012.
- J. Stallkamp, M. Schlipsing, J. Salmen, and C. Igel. Man vs. computer: Benchmarking machine learning algorithms for traffic sign recognition. *Neural Networks*, 2012. ISSN 0893-6080. doi: 10.1016/j.neunet.2012.02.016.